TANKLOGIX PORTAL

TICKET MANAGEMENT 3.0

CONTENTS

11	Lease Number	12 1
	Ticket Start Time	
	Ticket-Driver Image	
	Ticket Origin	
	Driver Name	
	CustomerID Driver ID	
	Customer Name	
	Ticket Batch Tag	
	Production Ticket ID	
	Ticket Number	
	Checkbox Column	
	INDIVIDUAL GRID COLUMNS	
(GRID INFORMATION	
	GRID HEADER FUNTIONALITY	
	TOP OF GRID CONTROLS	
	LEASE-WELL BULK EDITS	8
	MANUAL LEASE-WELL TICKET CREATION	7
	LEASE-WELL SEARCH	
	LEASE-WELL SEARCH, MANUAL TICKET CREATION, BULK EDITS	5
	CUSTOMERS / DRIVERS WINDOWS	4
	SITES	4
	TITLE AREA PAGE TOP	4
١	PAGE FEATURES	3
	Disposals > Ticket Management 3.0	3
١	PORTAL NAVIGATION	3
ı	NTRODUCTION	3

	Lease Number Full	12
	Lease Type	12
	RRC District	12
	Well Number	12
	RRC Lease Verified	13
	Volume BBLs	13
	Water Type	13
	Produced Water	13
	Disposal Lane	13
	Notes	13
	Created By / Edited By	13
	Create / Edit Date	13
	Actual Volume	13
	Entered Lease Name	13
	RRC Lease Name	13
	RRC Operator Name	14
	Accounting Code	14
	Row ID	14
Ν	OTIFICATIONS	14
IC	ONS AND SYMBOLS	14
\sim	THED INICODMATION	1.1


INTRODUCTION

Ticket Management 3.0 represents a significant change in several features of Ticket Management, including Wells management within leases, improved bulk edits and deletes, more streamlined interface, Ticket Batch Tag Deletes (in connection with CSV File uploads), and several bug fixes. Ticket Management is scheduled to replace all other versions of Ticket Management by year-end of 2017; Version 3.0 will be the only version with bug fixes applied from now and beyond.

PORTAL NAVIGATION

Disposals > Ticket Management 3.0


PAGE FEATURES



TITLE AREA PAGE TOP

- Question mark icon is link to http://blog.tanklogix.com and links and tutorials can be found there.
- Eye icon will toggle viewability of upper-page controls to maximize page real estate in certain situations
- Transmit Lease and Transmit Lease-Well info is the on-demand mechanism for scheduling a transfer of the latest Lease and/or Lease-Well information from the Portal to the HMI.





- Both the Leases and Leases-And-Wells allow you to select a site and schedule the download of fresh lease information to that site.
 - o For Leases, the most recent 100 Leases of "RRC Verified" information will be transmitted down to the site
 - o For Leases And Wells, there is a 1:Many relationship between Leases and Wells. We will transmit the first 400 lines of "RRC Verified" Lease:Well information to the site. The information is sorted by Lease and Well within Lease.
 - o These modals are triggered by the green and orange arrow icons.


SITES

You will see the sites you have been authorized to see by your administrator. Sorting and searching via Site Name or Box ID available now.

CUSTOMERS / DRIVERS WINDOWS

Additional functionality, sort/search provided for the Customers and Drivers dialog windows:






LEASE-WELL SEARCH, MANUAL TICKET CREATION, BULK EDITS

• Toggle control to save page space when lease info not needed. Click on eye icon to reveal Lease-Well search, Manual Lease-Well Ticket Creation, and Lease-Well Bulk Edits:

● HIDE LEASE-WELL SEARCH, MANUAL TICKET CREATION, BULK EDITS				
☐ LEASE-WELL SEARCH				
☐ MANUAL LEASE-WELL TICKET CREATION	☐ LEASE-WELL BULK EDITS			


LEASE-WELL SEARCH

- 1: Full-text search for all lease, well, operator, etc.
- 2: Individual field search for all lease, well, operator, etc. These will filter the results in the Search Box.
- 3: Well Information added throughout. Well information can originate from the Texas RRC monthly data files, OR from your own customer-supplied Lease-Well entries.
- 4: When this checkbox is checked, your selected entry in this box will be applied to all rows in the Grid that are in edit mode and then are saved. This checkbox is mutually exclusive to the Lease-Well Bulk Edits checkbox. These are two separate ways to bulk edit the Grid, can cannot be used together (to avoid unexpected interactions in the Grid).
- 5: Data source filter to filter RRC or Customer-Supplied originated Lease-Well info. Default is to use both.



MANUAL LEASE-WELL TICKET CREATION


- 1: Pre-fill some of these input boxes by clicking Copy Lease Search Info for any selected radio button in the Lease-Well Search results
- 2: Customer and Driver selections are made here, instead of up above in main Customer and Driver area.



Some items to note: It is permissible to create Duplicate ticket numbers from this panel. In some cases, this is the desired behavior.

LEASE-WELL BULK EDITS


- 1: Pre-fill some of these input boxes by clicking Copy Lease Search Info for any selected radio button in the Lease-Well Search results
- 2: Each data column has a value box and an Apply checkbox. In order for selections to be edited-transferred to the grid, the Apply box must be checked. In this example, if we selected Lease Number 112233 and wanted to change all selected rows in the grid with this Lease Number, we would click the Apply Bulk Edits green button to do this.
- 3: This button applies all checked values into the grid below, for all rows in Edit mode. These can be applied at a single time to as many rows as are in the
- 4: The grid reflects all changes from the bulk edits operations.
- Note: clicking the Lease-Well Bulk Edits checkbox, or the CLOSE links, will uncheck all Apply checkboxes. Textbox values persist.




TOP OF GRID CONTROLS




- 1: Search Date Range: Targets the Ticket Start Time for searching.
- 2: Search Grid: Although the grid auto-refreshes in many instances of UI changes, this will allow you to reset the grid results. When first coming into this Ticket Management 3.0 page, sometimes it is beneficial on the first search to click this button.
- 3: Customize Grid Columns: You may select which columns you want to appear in your grid and save that order. When you click this button, the following modal appears:



- 4: You may save the grid order of your grid. You can drag and drop with your mouse any column header and reposition the column left-to-right. Once you get the order how you wish, click the Save Grid Column Order button and the grid stays in that order during your session and when you come back to this page.
- 5: Opens a modal showing a grid of reporting any CSV manual uploading activity your company has had:



- 6: Tickets Search: Search for multiple tickets, each ticket number separated by a comma (,).
- 7: Download Grid contents to CSV or PDF
- 8: Delete Ticket Batch Tag: This allows you to remove a CSV manual batch tag (or any other group of tickets) that matches the Ticket Batch Tag field. This the former Ticket Split ID field renamed. It is short 5 characters only. But it allows a tag to delete if you need to remove an incorrect CSV upload. You set the Ticket Batch Tag in the CSV upload itself, or you can do this via Bulk Edits, or editing each line separately.



This is an example of how you would delete this ticket (and all others containing value A-223 in the Ticket Batch Tag) for a specific time date range. This checkbox is defaulted to be checked. If you do not check this, all tickets, regardless of Ticket Start Time, will be removed for this Ticket Batch Tag value.

GRID HEADER FUNTIONALITY



- 1: EDIT GRID (set all visible rows to edit mode): This button will open up to 10 rows max, every editable field/column in those rows, for editing as many cell combinations as desired. To close the edit mode of rows without saving, press button 2: Reset Grid. To Save all rows, press button 3: SAVE GRID ROWS. To DELETE rows, press button 4: DELETE selected grid rows. To save a single row (even if multiple rows are selected), place your cursor into an edited row, make your change, and with the cursor in a cell on that row, press Enter key. This is known as INLINE editing. And if yourcursor is in the grid and you press enter, it will save just that single row.
- 2: RESET GRID: Although the grid auto-refreshes in many instances of UI changes, this will allow you to reset the grid results.
- 3: SAVE GRID ROWS: This button will save as many checked rows as there are in your grid.
- 4: DELETE SELECTED GRID ROWS: This button will delete as many checked rows as there are in your grid.
- 5: The refresh grid does a new request to the database and refreshes the entire grid.

GRID INFORMATION

INDIVIDUAL GRID COLUMNS

Many columns are searchable with filters and sortable. Several fields are editable in this grid. With all grid editing, the total number of rows edited is what is visible. In a paginated results set, let's say we have 14 total rows of data and page 1 is set to display 10 rows, only the first 10 (all on page 1) will be edited.

Checkbox Column

This column will toggle all the checkboxes on. This can be used for Bulk Edit selection of rows. It does not open all cells for editing like the EDIT GRID button does; however, it can also be used to toggle in edit mode more than 10 rows at a time.

Ticket Number

An Integer type field to hold Ticket Info for a transaction

Production Ticket ID

This may be different from the Ticket Number, based on what programming and input it in place at the individual field HMI – site.

Ticket Batch Tag

A 5-character designator field to identify a group of records/rows. These can then be deleted in full by the DELETE Ticket Batch Tag button if needed.

Customer Name

Trucking company associated with this ticket.

CustomerID Driver ID

4-digit Customer ID and 4-digit Driver ID associated with this ticket.

Driver Name

Full text first and last name of name associated with Driver ID code within the context of a specific Customer ID.

Ticket Origin

May be PLC, TankWarden, Manual, or CSV.

Ticket-Driver Image

Link to driver image if one present.

Ticket Start Time

Local time valve was open to offload liquid.

Lease Number

Integer value for Lease Number associated with this ticket.

Lease Number Full

Zero-filled full Lease Number.

Lease Type

Oil or Gas.

RRC District

One of various defined Oil/Gas districts in the state of Texas.

Well Number

Alphanumeric representation of well number associated with a specific lease for a specific load.

RRC Lease Verified

If the Lease Number + RRC District + Gas-Oil Flag values equal the same info from either the Texas RRC monthly file or your Company's own Customer-Supplied Lease-Well info, then "YES" will appear in this column; otherwise, if there is not a valid match, "NO" will appear.

Volume BBLs

Self-explanatory.

Water Type

One of several preset values here in this dropdown.

Produced Water

Yes-No flag to tag if this transaction was produced water or not.

Disposal Lane

Lane number where truck offloaded liquid.

Notes

A 25-character text field that can be used to describe this transaction. In several post-P18 reports, the Notes field is part of the reporting.

Created By / Edited By

Username of person making edits to the grid.

Create / Edit Date

Date ticket was created or edited.

Actual Volume

BBL is field used. This field is exploratory for now.

Entered Lease Name

Future use.

RRC Lease Name

Official RRC Lease Name, based on monthly table lookup.

RRC O	perator Name				
Official	Official RRC Operator Name for this lease, based on monthly table lookup.				
Accou	nting Code				
	Deprecated for now, but could be used for a comment or tag.				
•					
Row ID					
Interna	Internal Use Only.				
NOTI	FICATIONS				
ICON	S AND SYMBOLS				
	ICONS AND SYMBOLS				
Togglin	Toggling the (icon will show/hide certain information. Clicking the (icon will send you to the TankLogix blog where tutorials and other helps can be found for this page.				
OTHE	R INFORMATION				
	Documentation Version / Author / Revision Date				
1	1.0 / Greg Bagley / November 13, 2017				